


# Android: HTC (IMAP)

This is a setup guide that will assist you in setting up your Hosted Mailbox on HTC mobile and tablet devices using IMAP.


1. Locate the "**Settings**" icon within your Apps Drawer.




2. Within Settings, scroll down and select "**Accounts and Sync**".




3. In the upper right, select "**Add**".



4. Select "**Mail**".



5. Enter the following information:
  - a. **"Email Address"**: example@unifyamerica.net
  - b. **"Password"**: Your email address password



6. Tap **"Next"**.
7. Enter the following information on the next screen:
  - a. **"Protocol"**: IMAP
  - b. **"Email address"**: example@unifyamerica.net
  - c. **"Username"**: example@unifyamerica.net

- d. **"Password"**: Your email address password
- e. **"IMAP Server"**: secure.emailsrvr.com
- f. **"Security type"**: SSL
- g. **"Server Port"**: 993

The image shows a mobile application screen titled "Incoming settings". It contains several input fields and dropdown menus. The fields are: Protocol (set to IMAP), Email address (user@domain.com), Username (user@domain.com), Password (masked with dots), IMAP server (secure.emailsrvr.com), Security type (SSL), and Server port (993). At the bottom, there are two buttons: "Back" and "Next". The "Next" button is highlighted with a red rectangular border.

- 8. Tap **"Next"**
- 9. Enter the following information on the next screen:
  - a. **"Login required"**: Checked
  - b. **"Username"**: example@unifyamerica.net
  - c. **"Password"**: Your email address password
  - d. **"SMTP Server"**: secure.emailsrvr.com
  - e. **"Security type"**: SSL
  - f. **"Server Port"**: 465

Outgoing server settings

✓ Login required

Username  
user@domain.com

Password  
\*\*\*\*\*

SMTP server  
secure.emailsrvr.com

Security type  
SSL

Server port  
465

Back Next

10. Within the "**Account Settings**" screen, adjust the items you wish to sync.

New account

Account name  
User@domain.com

Your name  
First Last

Back Finish setup

11. Tap "**Next**".

12. Success! Your HTC device should now begin syncing with your mailbox.